

1. IDENTIFICATION
- 1.1 Digital-8-24-U-Sym
- 1.2 Unsigned Decimal Print, Double Precision
- 1.3 January 19, 1966



2. ABSTRACT

This subroutine permits the typeout of a double-precision integer stored in the usual convention for double-precision numbers, (see Digital-8-13-F-Sym). The one exception is that all 24 bits are interpreted as magnitude bits (i.e. the bit "0" of the high-order word is not a sign bit). The typeout is in the form of a seven-digit, positive, decimal integer.

3. REQUIREMENTS

3.1 Storage

This subroutine requires (73) locations.

3.2 Subprograms and/or Subroutines (none)

3.3 Equipment

Basic PDP-8 with ASR-33

4. USAGE

4.1 Loading

The symbolic tape provided is assembled with either PAL III or MACRO-8. It may be assembled with the user program or separately with the proper origin setting. Neither origin setting nor "\$" terminating character exists on the tape, but the tape does have a PAUSE on the end.

4.2 Calling Sequence

This subroutine is called by an effective JMS UDPRNT. The location immediately following the calling JMS contains the address of the high-order portion of the double-precision integer stored in the usual double-precision format.

5. RESTRICTIONS (none)

6. DESCRIPTION

6.1 Discussion

This is basic double-precision subroutine used to obtain decimal output corresponding to double-precision, binary words. First, the binary equivalent of 10,000,000 is subtracted from the original number until under-flow occurs. A count is kept of the number of subtractions necessary to accomplish this, thus yielding the most significant decimal digit. Then this digit is added to 2608 and printed on the ASR-33 through the AC. This process is repeated using the proper power of ten to give the seven remaining digits.

6.2 Examples and/or Applications (none)

6.3 Scaling

The numbers are interpreted and typed out as integers.

7. METHOD (See Digital-8-22-U-Sym)

8. FORMAT

8.1 Input Data (Not Applicable)

8.2 Core Data

The double-precision integers are stored in the usual double-precision format, (see Digital-8-13-F-Sym), with the exception that bit "0" of the high-order word is interpreted as part of the number not a sign bit.

8.3 Output Data

Output is in the form of eight consecutive decimal digits. No sign is printed. Spacing, tabulation, carriage return, etc., are not provided for in this subroutine. See Digital-8-19-U-Sym which contains short subroutines for those purposes.

9. EXECUTION TIME

9.1 Minimum (Not Applicable)

9.2 Maximum (Not Applicable)

9.3 Average

This subroutine is output limited at 10 cps by the ASR-33

10. PROGRAM

10.1 Core Map (none)

10.2 Dimension List(s) (none)

10.3 Macro, Parameter, and Variable Lists (none)

10.4 Program Listing

```
      /CHECK OUTB PROGRAM FOR UNSIGNED , DOUBLE-PRECISION PRINT
      *200
      RETURN=JMS TYGR
      PRINT=JMS UDPRNT
      SPACE=JMS TYSP
      DEFINE DBLADD A B
      <CLA CLL; TAD A+1; TAD B+1; DCA A+1; RAL; TAD A ;TAD B; DCA A
      DEFINE DSHFT C D
      <CLA CLL; TAD C; RAL; DCA C ;TAD D; RAL; DCA D>
      DEFINE DMOVE E F
      <CLA; TAD E; DCA F; TAD E+1; DCA F+1>
0200  4777      RETURN
0201  7300      CLA CLL
0202  3305      DCA TEMP
0203  3306      DCA TEMP+1
0204  1374      TAD (-5)
0205  3313      DCA COUNT1
0206  1373      TAD (-2)
```

2. ABSTRACT

This subroutine permits the typeout of a double-precision integer stored in the usual convention for double-precision numbers, (see Digital-8-13-F-Sym). The one exception is that all 24 bits are interpreted as magnitude bits (i.e. the bit "0" of the high-order word is not a sign bit). The typeout is in the form of a seven-digit, positive, decimal integer.

3. REQUIREMENTS

3.1 Storage

This subroutine requires (73) locations.

3.2 Subprograms and/or Subroutines (none)

3.3 Equipment

Basic PDP-8 with ASR-33

4. USAGE

4.1 Loading

The symbolic tape provided is assembled with either PAL III or MACRO-8. It may be assembled with the user program or separately with the proper origin setting. Neither origin setting nor "\$" terminating character exists on the tape, but the tape does have a PAUSE on the end.

4.2 Calling Sequence

This subroutine is called by an effective JMS UDPRNT. The location immediately following the calling JMS contains the address of the high-order portion of the double-precision integer stored in the usual double-precision format.

5. RESTRICTIONS (none)

6. DESCRIPTION

6.1 Discussion

This is basic double-precision subroutine used to obtain decimal output corresponding to double-precision, binary words. First, the binary equivalent of 10,000,000 is subtracted from the original number until under-flow occurs. A count is kept of the number of subtractions necessary to accomplish this, thus yielding the most significant decimal digit. Then this digit is added to 2608 and printed on the ASR-33 through the AC. This process is repeated using the proper power of ten to give the seven remaining digits.

6.2 Examples and/or Applications (none)

6.3 Scaling

The numbers are interpreted and typed out as integers.

7. METHOD (See Digital-8-22-U-Sym)

8. FORMAT

8.1 Input Data (Not Applicable)

8.2 Core Data

The double-precision integers are stored in the usual double-precision format, (see Digital-8-13-F-Sym), with the exception that bit "0" of the high-order word is interpreted as part of the number not a sign bit.

8.3 Output Data

Output is in the form of eight consecutive decimal digits. No sign is printed. Spacing, tabulation, carriage return, etc., are not provided for in this subroutine. See Digital-8-19-U-Sym which contains short subroutines for those purposes.

9. EXECUTION TIME

9.1 Minimum (Not Applicable)

9.2 Maximum (Not Applicable)

9.3 Average

This subroutine is output limited at 10 cps by the ASR-33

10. PROGRAM

10.1 Core Map (none)

10.2 Dimension List(s) (none)

10.3 Macro, Parameter, and Variable Lists (none)

10.4 Program Listing

```
      /CHECK OUTB PROGRAM FOR UNSIGNED , DOUBLE-PRECISION PRINT
      *200
      RETURN=JMS TYCR
      PRINT=JMS UDPRNT
      SPACE=JMS TYSP
      DEFINE DBLADD A B
      <CLA CLL; TAD A+1; TAD B+1; DCA A+1; RAL; TAD A ;TAD B; DCA A
      DEFINE DSHFT C D
      <CLA CLL; TAD C; RAL; DCA C ;TAD D; RAL; DCA D>
      DEFINE DMOVE E F
      <CLA; TAD E; DCA F; TAD E+1; DCA F+1>
0200  4777      INITL,      RETURN
0201  7300          CLA CLL
0202  3305          DCA TEMP
0203  3306          DCA TEMP+1
0204  1374          TAD (-5)
0205  3313          DCA COUNT1
0206  1373          TAD (-2)
```

| | | | |
|------|------|-------|-----------------------|
| 0207 | 3314 | | DCA COUNT2 |
| 0210 | 4777 | | RETURN |
| 0211 | 4776 | TOP, | PRINT; |
| 0212 | 0307 | DNUMB | |
| 0213 | 4775 | | SPACE |
| 0214 | 7300 | | DBLADD DNUMB,VARCON |
| 0215 | 1310 | | |
| 0216 | 1312 | | |
| 0217 | 3310 | | |
| 0220 | 7004 | | |
| 0221 | 1307 | | |
| 0222 | 1311 | | |
| 0223 | 3307 | | |
| 0224 | 2313 | | ISZ COUNT1 |
| 0225 | 5211 | | JMP TOP |
| 0226 | 4777 | FIVE, | RETURN |
| 0227 | 1374 | | TAD (-5) |
| 0230 | 3313 | | DCA COUNT1 |
| 0231 | 2314 | | ISZ COUNT2 |
| 0232 | 5211 | | JMP TOP |
| 0233 | 1373 | | TAD (-2) |
| 0234 | 3314 | | DCA COUNT2 |
| 0235 | 7200 | | DMOVE VARCON, TEMP |
| 0236 | 1311 | | |
| 0237 | 3305 | | |
| 0240 | 1312 | | |
| 0241 | 3306 | | |
| 0242 | 7300 | | DSHFT VARCON+1,VARCON |
| 0243 | 1312 | | |
| 0244 | 7004 | | |
| 0245 | 3312 | | |
| 0246 | 1311 | | |
| 0247 | 7004 | | |
| 0250 | 3311 | | |
| 0251 | 7300 | | DSHFT VARCON+1,VARCON |
| 0252 | 1312 | | |
| 0253 | 7004 | | |
| 0254 | 3312 | | |
| 0255 | 1311 | | |
| 0256 | 7004 | | |
| 0257 | 3311 | | |
| 0260 | 7300 | | DBLADD VARCON,TEMP |
| 0261 | 1312 | | |
| 0262 | 1306 | | |
| 0263 | 3312 | | |
| 0264 | 7004 | | |
| 0265 | 1311 | | |
| 0266 | 1305 | | |
| 0267 | 3311 | | |
| 0270 | 7300 | | DSHFT VARCON+1,VARCON |
| 0271 | 1312 | | |
| 0272 | 7004 | | |
| 0273 | 3312 | | |
| 0274 | 1311 | | |
| 0275 | 7004 | | |
| 0276 | 3311 | | |
| 0277 | 7200 | | DMOVE VARCON,DNUMB |
| 0300 | 1311 | | |

```

0301 3307
0302 1312
0303 3310
0304 5211          JMP TOP
0305 0000  TEMP, DUBL 0
0306 0000
0307 0000  DNUMB, DUBL 0
0310 0000
0311 0000  VARCON, DUBL 1
0312 0001
0313 0000  COUNT1, 0
0314 0000  COUNT2, 0
0373 7776  PAGE
0374 7773
0375 0627
0376 0400
0377 0617

        PAUSE

        /UNSIGNED DECIMAL PRINT, DOUBLE PRECISION
        /CALLING SEQUENCE:  JMS UDPRNT /SUBROUTINE CALLED
        /                   HI ADDR   /ADDRESS OF HIGH ORDER WORD
        /                   RETURN   /RETURN WITH AC AND L CLEAR

0200 0000  UDPRNT, 0
0201 7300          CLA CLL
0202 1600          TAD I UDPRNT          /PICK UP ADDRESS OF HIGH-ORDER WORD
0203 3267          DCA UDGET
0204 1667          TAD I UDGET          /PICK UP BOTH WORDS FOR USE IN SUBROUTIN
0205 3261          DCA UDHIGH
0206 2267          ISZ UDGET
0207 1667          TAD I UDGET
0210 3262          DCA UDLOW
0211 1255          TAD UDLOOP          /INITIALIZE DIGIT COUNTER FOR "8"
0212 3260          DCA UDCNT
0213 1256          TAD UDADDR          /INITIALIZE TO TABLE OF POWERS OF TEN
0214 3270          DCA UDPTR
0215 2200          ISZ UDPRNT          /INDEX LINKAGE FOR CORRECT RETURN
0216 1670  UDARND, TAD I UDPTR          /PICK UP CURRENT POWER OF TEN FOR
0217 2270          ISZ UDPTR          /USE IN SUBTRACTION
0220 3263          DCA UDHSUB
0221 1670          TAD I UDPTR
0222 2270          ISZ UDPTR
0223 3264          DCA UDLSUB
0224 7100  UDDO,   CLL          /DOUBLE PRECISION SUBTRACTION
0225 1264          TAD UDLSUB
0226 1262          TAD UDLOW
0227 3266          DCA UDTEML
0230 7004          RAL
0231 1263          TAD UDHSUB
0232 1261          TAD UDHIGH
0233 7420          SNL          /DID IT UNDERFLOW?
0234 5242          JMP UDOUT          /NO, COUNT IS DONE
0235 2265          ISZ UDBOX          /YES, COUNT NOT DONE YET. INDEX DIGIT
0236 3261          DCA UDHIGH          /DEPOSIT REMAINING PORTIONS OF WORD
0237 1266          TAD UDTEML
0240 3262          DCA UDLOW

```


| | | | | | |
|------|------|---------|--------------|--|-----------------------------------|
| 0241 | 5224 | | JMP UDDO | | /GO BACK AND SUBTRACT AGAIN |
| 0242 | 7200 | UDOUT, | CLA | | |
| 0243 | 1265 | | TAD UDBOX | | /PICK UP RESULTING DIGIT |
| 0244 | 1257 | | TAD UDTWO | | /ADD "260" TO IT |
| 0245 | 6046 | | TLS | | /TYPE IT OUT |
| 0246 | 6041 | | TSF | | |
| 0247 | 5246 | | JMP .-1 | | |
| 0250 | 7300 | | CLA CLL | | |
| 0251 | 3265 | | DCA UDBOX | | /INITIALIZE DIGIT TO "0" |
| 0252 | 2260 | | ISZ UDCNT | | /HAVE WE TYPED "8" DIGITS |
| 0253 | 5216 | | JMP UDARND | | /NO, DETERMINE NEXT DIGIT |
| 0254 | 5600 | | JMP I UDPRNT | | /YES, SUBROUTINE DONE. RETURN |
| 0255 | 7770 | UDLOOP, | -10 | | /COUNT OF "8" DIGITS |
| 0256 | 0271 | UDADDR, | UDCON1 | | /INITIAL ADDRESS OF POWERS OF TEN |
| 0257 | 0260 | UDTWO, | 260 | | /ICODE FOR DIGITS |
| 0260 | 0000 | UDCNT, | 0 | | /STORAGE LOCATIONS |
| 0261 | 0000 | UDHIGH, | 0 | | |
| 0262 | 0000 | UDLOW, | 0 | | |
| 0263 | 0000 | UDHSUB, | 0 | | |
| 0264 | 0000 | UDLSUB, | 0 | | |
| 0265 | 0000 | UDBOX, | 0 | | |
| 0266 | 0000 | UDTEML, | 0 | | |
| 0267 | 0000 | UDGET, | 0 | | |
| 0270 | 0000 | UDPTR, | 0 | | |
| 0271 | 3166 | UDCON1, | 3166 | | /POWERS OF TEN |
| 0272 | 4600 | | 4600 | | /-10,000,000 |
| 0273 | 7413 | | 7413 | | /-1,000,000 |
| 0274 | 6700 | | 6700 | | |
| 0275 | 7747 | | 7747 | | /-100,000 |
| 0276 | 4540 | | 4540 | | |
| 0277 | 7775 | | 7775 | | /-10,000 |
| 0300 | 4360 | | 4360 | | |
| 0301 | 7777 | | 7777 | | /-1,000 |
| 0302 | 6030 | | 6030 | | |
| 0303 | 7777 | | 7777 | | /-100 |
| 0304 | 7634 | | 7634 | | |
| 0305 | 7777 | | 7777 | | /-10 |
| 0306 | 7766 | | 7766 | | |
| 0307 | 7777 | | 7777 | | /-1 |
| 0310 | 7777 | | 7777 | | |
| | | PAUSE | | | |

Digital-8-24-U-Sym
Page 6

UDADDR 0256
UDARND 0216
UDBOX 0265
UDCNT 0260
UDCON1 0271
UDDO 0224
UDGET 0267
UDHIGH 0261
UDHSUB 0263
UDLOOP 0255
UDLOW 0262
UDLSUB 0264
UDOUT 0242
UDPRNT 0200
UDPTR 0270
UDTEML 0266
UDTWO 0257

00000000 00000001 00000002 00000003 00000004
00000005 00000006 00000007 00000008 00000009
00000010 00000020 00000030 00000040 00000050
00000060 00000070 00000080 00000090 00000100
00000100 00000200 00000300 00000400 00000500
00000600 00000700 00000800 00000900 00001000
00001000 00002000 00003000 00004000 00005000
00006000 00007000 00008000 00009000 00010000
00010000 00020000 00030000 00040000 00050000
00060000 00070000 00080000 00090000 00100000
00100000 00200000 00300000 00400000 00500000
00600000 00700000 00800000 00900000 01000000
01000000 02000000 03000000 04000000 05000000
06000000 07000000 08000000 09000000 10000000
10000000 03222784 13222784 06445568 1

11 DIAGRAMS

11.1 Flow Charts



