DNOSTIPE Object Installation

Part No. 2276583-9701 *B
1 December 1983

READ FISH

© Texas Instruments Incorporated 1982, 1983

All Rights Reserved, Printed in U.S.A.

The information and/or drawings set forth in this document and all rights in and to inventions disclosed herein and patents which might be granted thereon disclosing or employing the materials, methods, techniques or apparatus described herein, are the exclusive property of Texas Instruments Incorporated.

Contents

Title

Section 1 -- Introduction

Section 2 -- Preparing for Installation

Section 3 -- Installing TIPE

Section 4 -- Preparing for International Installation

Section 5 -- Installing TIPE International

| READ THIS DOCUMENT BEFORE ATTEMPTING TO USE THIS OBJECT KIT. |
| THIS DOCUMENT DESCRIBES THE 2.1.0 (OR LATER) VERSION OF THE |
| DNOS TIPE OBJECT INSTALLATION MEDIA, PART NUMBER 2302562- |
| 1602, 2302562-1603, AND 2302562-1604 (DISKETTE), OR 2302562- |
| 1601 (OTHER).

 $\c | \c TEXAS$ INSTRUMENTS ASSUMES NO RESPONSIBILITY FOR MODIFICATIONS $\c | \c MADE$ TO THIS OBJECT KIT.

Section 1

Introduction

1.1 GENERAL INFORMATION

This manual describes the procedures used to install both the Texas Instrument Page Editor (TIPE) and TIPE International software from the TI supplied media onto a disk using the DNOS Operating System. TIPE is the standard United States version and TIPE International is the international version that supports the following languages:

- * German
- * Danish
- * Spanish
- * French
- * Italian
- * Norwegian
- * Dutch
- * Swedish
- * Finnish

Be sure to copy and/or write protect the installation media. For copy procedures, refer to the <u>DNOS Operations Guide</u>, part number 2270502-9701.

Consult the Release Information (included in the Product Documentation Package) and apply any required patches before attempting this installation.

1.2 MEDIA DEFINITION

The installation instructions differ according to the type of kit ordered. You can receive the DNOS TIPE program on either disk or magnetic tape. The disk version can be either an

add-on package for other purchased software or a separate disk.

The TIPE software package is shipped in three formats:

- * Disk -- Three FD1000 diskettes, DS10, DS25, DS50, DS80, DS200, DS300, or CD1400 disk pack that contains the TIPE object
- * Magnetic Tape -- An 800 or 1600 bits-per-inch (bpi) magnetic tape reel or magnetic tape cartridge that contains the TIPE object
- * Add-on -- A disk pack that contains the TIPE object and one or more other products

The product documentation package includes a disk map of the contents of the media.

1.3 INSTALLATION PROCEDURE

The object media contains the files and batch streams that install TIPE. You can install TIPE as follows:

- 1. Load the TIPE software media.
- 2. Specify the use of special System Command Interpreter (SCI) commands.
- 3. Install TIPE 2.1.0 program and related SCI commands.
- 4. Install TIPE 2.1.0 International program.
- 5. Edit the Initialize System (IS) system command procedure.

1.4 SYSTEM REQUIREMENTS

To install TIPE, you must have a functioning DNOS Operating System, Release 1.2 or later.

Section 2

Preparing for Installation

2.1 INTRODUCTION

The following paragraphs explain how to prepare the media containing TIPE for installation. Turn to the paragraph describing the media you are using.

NOTE

In the prompt displays in this document, the responses you should enter are shown to the right of the colons. However, you must supply all prompt responses that appear in angle brackets (<>). For example, if <disk drive> appears after a prompt, you must enter the system name of the disk drive which you are using.

2.2 DISK FORMAT

If you receive TIPE on FD1000 diskettes, use the following steps to prepare it for installation:

- 1. Remove the write-protect tabs from the diskettes since you will only read from these diskettes.
- 2. Place the diskette with the volume name TIPEINSN in an available diskette drive on a functioning DNOS Operating System, Release 1.2 or later.
- 3. Install the volume TIPEINSN by entering the Install Volume (IV) command in response to the SCI command prompt ([]):

[] IV

4. Respond to the IV prompts as follows. responses you enter are shown to the right of the colons in this example:

INSTALL VOLUME

UNIT NAME: <disk drive> VOLUME NAME: TIPEINSN

- * UNIT NAME: Enter the name of the disk drive in which you inserted TIPEINSN. For example, enter DS02 if you installed the volume in the disk drive designated as 02 on your system.
- * VOLUME NAME: Enter the volume name TIPEINSN.
- 5. Proceed to Section 3 to complete the installation.

If you receive TIPE on a DS10, DS25, DS50, DS80, DS200, DS300, or CD1400, use the following steps to prepare the media for installation:

- 1. Leave the write protect on since you will not write to this disk.
- 2. Place the disk with the volume name TIPEN in an available disk drive on a functioning DNOS Operating System, Release 1.2 or later, and load it.
- 3. Install the volume TIPEN by entering the Install Volume (IV) command in response to the SCI command prompt ([]):

[] IV

4. Respond to the IV prompts as follows. responses you enter are shown to the right of the colons in this example:

INSTALL VOLUME

UNIT NAME: <disk drive> VOLUME NAME: TIPEN

- * UNIT NAME: Enter the name of the disk drive in which you inserted TIPEN For example, enter DSO2 if you installed the volume in the disk drive designated as 02 on your system.
- * VOLUME NAME: Enter the volume name TIPEN
- 5. Use the Assign Synonym (AS) command to assign the synonym TIPEINSN to the pathname of the TIPE directory.

Enter the AS command after the SCI prompt ([]):

[] AS

6. Respond to the AS prompts as follows:

ASSIGN SYNONYM VALUE

SYNONYM: TIPEINSN VALUE: TIPEN.TIPEINSN

- * SYNONYM: Enter the synonym TIPEINSN.
- * VALUE: Enter the pathname TIPEN.TIPEINSN.
- 7. Proceed to Section 3 to complete the installation.

2.3 MAGNETIC TAPE FORMAT

If you receive TIPE on magnetic tape reel or magnetic tape cartridge, you must first move the files from the magnetic tape to a disk before installing TIPE on your system. To do this, use the following steps:

- 1. Create a directory on a disk of your choice by entering the Create Directory File (CFDIR) command in response to the SCI prompt ([]):
 - [] CFDIR
- 2. Respond to the CFDIR prompts as follows:

CREATE DIRECTORY FILE

PATHNAME: <volume>.TIPEN

MAX ENTRIES: 3

DEFAULT PHYSICAL RECORD SIZE:

- PATHNAME: Enter the name of the volume name of the disk on which you are creating the directory, enter a period, and then enter TIPEN as the name of the directory on this disk.
- * MAX ENTRIES: Enter 3 as the maximum number of files the directory can hold.
- DEFAULT PHYSICAL RECORD SIZE: RETURN to leave this prompt blank.
- 3. Load the magnetic tape reel or cartridge on an available tape drive.

4. Move the contents of the magnetic tape reel or cartridge to the directory you created by entering the Restore Directory (RD) command in response to the SCI prompt ([]):

[] RD

5. Respond to the RD prompts as follows:

RESTORE DIRECTORY

SEQUENTIAL ACCESS NAME: <tape drive> DIRECTORY PATHNAME: <volume>.TIPEN CONTROL ACCESS NAME: LISTING ACCESS NAME: <listing> OPTIONS: REPLACE EXECUTION MODE (F,B): FOREGROUND

- * SEQUENTIAL ACCESS NAME: Enter the name of the drive on which you loaded the tape. For example, enter MTO1 if you loaded the magnetic tape on the tape drive designated Ol in your system.
- * DIRECTORY PATHNAME: Enter the name of the volume you supplied for this procedure, enter a period, and then enter TIPEN.
- * CONTROL ACCESS NAME: Press RETURN to leave this prompt blank.
- LISTING ACCESS NAME: Enter the pathname of the file or the system name of the device where you want to store or print the RD listing. For example, to display the RD listing on your video terminal, press RETURN to leave this prompt blank. To print the listing on a printer, enter the system name of the printer (for example, LPO1).
- * OPTIONS: Enter REPLACE if the directory <volume>.TIPEN already exists and you want to replace its contents with the directory you are restoring. Otherwise, press RETURN to leave this prompt blank.
- * EXECUTION MODE (F,B): Enter (foreground) to execute the task in foreground mode.
- 6. After restoring the directory, unload the magnetic tape reel or cartridge.
- 7. Use the Assign Synonym (AS) command to assign

synonym TIPEINSN to the pathname of the directory which now contains TIPE. Enter the AS command after the SCI prompt ([]):

[] AS

8. Respond to the AS prompts as follows:

ASSIGN SYNONYM VALUE

SYNONYM: TIPEINSN VALUE: <volume>.TIPEN.TIPEINSN

- SYNONYM: Enter the synonym TIPEINSN.
- * VALUE: Enter the pathname directory that contains TIPE. The pathname includes the volume name of the disk, followed by a period and then the directory name TIPEN.TIPEINSN
- 9. Proceed to Section 3 to complete the installation.

2.4 ADD-ON FORMAT

If TIPE is included on the system disk that is being used, it is contained in the directory .TIPEN. Proceed to step 4 to assign the synonym TIPEINSN. However, If TIPE is provided as an add-on package on another disk, use the following steps to prepare it for installation:

- 1. Load the disk that contains the add-on package an available disk drive.
- 2. To install the disk, enter the Install Volume (IV) command in response to the SCI prompt ([]):

[] IV

3. Respond to the IV prompts as follows:

INSTALL VOLUME

UNIT NAME: <disk drive> VOLUME NAME: <volume name>

* UNIT NAME: Enter the name of the disk drive in which you loaded the disk containing the add-on package. example, enter DS02 if you loaded the addon disk in the disk drive designated as 02 on your system.

- * VOLUME NAME: Enter the volume name of the disk containing the add-on package.
- 4. Use the Assign Synonym (AS) command to assign the synonym TIPEINSN to the pathname of the directory that contains TIPE. Enter the AS command after the SCI prompt ([]):

[] AS

5. The prompts then appear on your screen. responses you enter are shown to the right of the colons in the following example:

ASSIGN SYNONYM VALUE

SYNONYM: TIPEINSN VALUE: <volume>.TIPEN.TIPEINSN

- * SYNONYM: Enter the synonym TIPEINSN.
- * VALUE: Enter the pathname of the directory that contains TIPE. The pathname includes the volume name of the disk, followed by a period and then the directory name TIPEN.TIPEINSN
- 6. Proceed to Section 3 to complete the installation.

Section 3

Installing TIPE

3.1 INTRODUCTION

A special SCI command library is included to help you install TIPE. During the installation, this library becomes the primary library and the system SCI command library becomes the secondary library. All system SCI commands are functional while the special SCI command library is active.

Use the following procedure to install TIPE:

- 1. Activate the special SCI command library by
 entering the .USE command in response to the SCI
 prompt ([]):
 - [] .USE TIPEINSN.S\$CMDS,.S\$CMDS
- 2. While the special SCI command library is in effect, the system displays the following menu on your screen:

TIPE

INSTALLATION

C O M M A N D S

<VERSION: 2.1.0 83342>

You may now use the following commands to install TIPE:

INSTALL - Install TIPE 2.1.0

RTN - Return to using system commands library

If the menu does not appear on your screen, return to step 1 and reenter the .USE command. If the menu still does not appear, take the following action:

- a. If you received TIPE in disk format, use the Show Volume Status (SVS) command to ensure that the disk volume is properly installed. If it is not, return to step 3 in paragraph 2.2 and install the volume again.
- b. If you received TIPE in the magnetic tape or add-on format, use the List Synonym (LS) command to ensure that the synonym TIPEINSN is assigned to the appropriate directory. If it is not, return to either step 7 in paragraph 2.3 (magnetic tape format) or step 4 in paragraph 2.4 (add-on format).

3.2 INSTALL TIPE AND SPECIAL SCI COMMANDS

To install the new release of TIPE, use the INSTALL command. This command copies the TIPE object to a directory named <volume>.S\$TIPE on the disk indicated. If any previous directory named <volume>.S\$TIPE already exists, it is deleted. Proceed as follows:

- 1. Enter INSTALL after the SCI prompt ([]):
 - [] INSTALL
- 2. Respond to the INSTALL prompts as follows:

INSTALL TIPE < VERSION 2.1.0 83342>
TIPE INSTALLATION DISK: TIPEINSN
SCI COMMAND LIBRARY: .S\$CMDS
SYSTEM DISK VOLUME: <volume>
TIPE DESTINATION VOLUME: <volume>
HIGHEST TERMINAL NUMBER: 20
TIPE BATCH LISTING: .TIPE\$IS

- * TIPE INSTALLATION DISK: If you received TIPE in the disk format, enter the volume name of the disk. If you received TIPE in the magnetic tape or add-on format, enter the synonym for the directory containing the software.
- * SCI COMMAND LIBRARY: Enter .SCMDS to specify the name of the SCI command library where the TIPE SCI procedures will be installed.
- * SYSTEM DISK VOLUME: Enter the name of the system disk that will be installed when you use TIPE. The TIPE message files will

be stored on this disk.

- * TIPE DESTINATION VOLUME: Enter the name of the volume where TIPE will be installed. All local TIPE directories will be stored on this volume.
- * HIGHEST TERMINAL NUMBER: Enter the highest number used in the system names of the terminals on your system. For example, if you have five terminals on your system and they are designated STO1, STO2, STO5, ST10, and ST20, enter 20.
- * TIPE BATCH LISTING: Enter .TIPE\$IS to specify the file on the system disk where the batch listing is to be stored.
- 3. The installation takes about 15 to 20 minutes to complete. When the installation completes successfully the following message is displayed:

TIPE installation completed with 0 errors

If you are installing an international version of TIPE, proceed to Section 4.

3.3 UNLOAD TIPE INSTALLATION DISK

If you install TIPE from magnetic tape, simply unload the magnetic tape and refer to paragraph 3.4 to complete the installation. However, if you installed TIPE from a disk, you must unload the disk before using TIPE. You must also return to the system SCI command library and edit the IS command in the system default command library (.SCMDS). Proceed as follows:

1. To return to the system command library where you will unload the disk, enter the special command RTN after the SCI prompt ([]):

[] RTN

2. To unload the disk, enter the SCI command Unload Volume (UV) after the SCI prompt ([]):

[] UV

3. Respond to the UV prompt as follows:

UNLOAD VOLUME VOLUME NAME: <volume>

* VOLUME NAME: Enter the volume name of the TIPE installation disk.

3.4 VERIFY TIPE INSTALLATION

To verify the installation, enter the TIPE command in response to the SCI command prompt ([]). If the TIPE main menu appears on your screen, you have successfully installed TIPE.

Section 4

Preparing for International Installation

4.1 INTRODUCTION

The following paragraphs explain how to prepare the media containing International TIPE for installation. Turn to the paragraph describing the media you are using.

4.2 DISK FORMAT

If you receive TIPE on FD1000 diskettes, use the following steps to prepare it for installation:

- 1. Remove the write protect tabs from the diskettes since you will only read from these diskettes.
- 2. Place the diskette with the volume name TFINTLN1 or TFINTLN2, depending on the language you want, in an available diskette drive on a functioning DNOS Operating System, Release 1.2 or later.
 - * TFINTLN1 is the diskette for:
 - German
 - Danish
 - Spanish
 - French
 - Italian
 - * TFINTLN2 is the diskette for:
 - Norwegian
 - Dutch
 - Swedish
 - Finnish
- 3. Install the volume TFINTLNx by entering the Install

Volume (IV) command in response to the SCI command prompt ([]):

[] IV

4. Respond to the IV prompts as follows. responses you enter are shown to the right of the colons in this example:

INSTALL VOLUME

UNIT NAME: <disk drive> VOLUME NAME: TFINTLNx

- * UNIT NAME: Enter the name of the disk drive in which you inserted TFINTLNx. For example, enter DSO2 if you installed the volume in the disk drive designated as 02 on your system.
- * VOLUME NAME: Enter the volume name TFINTLN1 or TFINTLN2, depending on the language you want.
- 5. Proceed to Section 5 to complete the installation.

you receive TIPE on a DS10, DS25, DS50, DS80, DS200, DS300, or CD1400, use the following steps to prepare the media for installation:

- 1. Leave the write protect on since you will not write to this disk.
- 2. Place the disk with the volume name TIPEN in an available disk drive on a functioning DNOS Operating System, Release 1.2 or later, and load it.
- 3. Install the volume TIPEN by entering the Install Volume (IV) command in response to the SCI command prompt ([]):

[] IV

4. Respond to the IV prompts as follows. responses you enter are shown to the right of the colons in this example:

INSTALL VOLUME

UNIT NAME: <disk drive> VOLUME NAME: TIPEN

* UNIT NAME: Enter the name of the disk drive in which you inserted TIPEN For example, enter DS02 if you installed the volume in the disk drive designated as 02 on your system.

- * VOLUME NAME: Enter the volume name TIPEN
- 5. Use the Assign Synonym (AS) command to assign the synonym TFINTLN1 or TFINTLN2, depending on the language you want, to the pathname of the TIPE International directory.
 - * TIPEN.TFINTLN1 is the diskette for:
 - German
 - Danish
 - Spanish
 - French
 - Italian
 - * TIPEN.TFINTLN2 is the diskette for:
 - Norwegian
 - Dutch
 - Swedish
 - Finnish Enter the AS command after the SCI prompt ([]):

[] AS

6. Respond to the AS prompts as follows:

ASSIGN SYNONYM VALUE SYNONYM: TFINTLNx

VALUE: TIPEN.TFINTLNx

- * SYNONYM: Enter the synonym TFINTLN1 or TFINTLN2, depending on the language you want.
- Enter the pathname TIPEN.TFINTLN1 or TIPEN.TFINTLN2, depending on language you want.
- 7. Proceed to Section 5 to complete the installation.

4.3 MAGNETIC TAPE FORMAT

If you receive TIPE on magnetic tape reel or magnetic tape cartridge, you must first move the files from the magnetic tape to a disk before installing TIPE on your system. If you have already installed the United States version of TIPE, the files have been moved from the magnetic tape to a disk; if you have not installed the United States version, go back to Section 2 and proceed as directed.

following steps to prepare for international the installation:

- 1. Use the Assign Synonym (AS) command to assign the synonym TFINTLN1 or TFINTLN2, depending on the language you want, to the pathname of the directory which now contains TIPE International.
 - <volume>.TIPEN.TFINTLNl is the directory for:
 - German
 - Danish
 - Spanish
 - French
 - Italian
 - <volume>.TIPEN.TFINTLN2 is the directory for:
 - Norwegian
 - Dutch
 - Swedish
 - Finnish

Enter the AS command after the SCI prompt ([]):

[] AS

2. Respond to the AS prompts as follows:

ASSIGN SYNONYM VALUE

SYNONYM: TFINTLNx

VALUE: <volume>.TIPEN.TFINTLNx

- * SYNONYM: Enter the synonym TFINTLN1 or TFINTLN2 depending on the language you want.
- 3. Proceed to Section 5 to complete the installation.

4.4 ADD-ON FORMAT

If TIPE is included on the system disk that is being used, it is contained in the directory .TIPEN. Proceed to step 4 to assign the synonym TFINTLNx. However, If TIPE is provided as an add-on package on another disk, use the following steps to prepare it for installation:

- Load the disk that contains the add-on package in an available disk drive.
- 2. To install the disk, enter the Install Volume (IV) command in response to the SCI prompt ([]):

[] IV

3. Respond to the IV prompts as follows:

INSTALL VOLUME

UNIT NAME: <disk drive>
VOLUME NAME: <volume name>

- * UNIT NAME: Enter the name of the disk drive in which you loaded the disk containing the add-on package. For example, enter DSO2 if you loaded the add-on disk in the disk drive designated as 02 on your system.
- * VOLUME NAME: Enter the volume name of the disk containing the add-on package.
- 4. Use the Assign Synonym (AS) command to assign the synonym TIPEINSN to the pathname of the directory that contains TIPE.

- <volume>.TIPEN.TFINTLN1 is the directory for:
 - German
 - Danish
 - Spanish
 - French
 - Italian
- <volume>.TIPEN.TFINTLN2 is the diskette for:
 - Norwegian
 - Dutch
 - Swedish
 - Finnish

Enter the AS command after the SCI prompt ([]):

[] AS

5. The prompts then appear on your screen. responses you enter are shown to the right of the colons in the following example:

ASSIGN SYNONYM VALUE

SYNONYM: TFINTLNx VALUE: <volume>.TIPEN.TFINTLNx

- * SYNONYM: Enter the synonym TFINTLN1 or TFINTLN2, depending on the language wanted.
- VALUE: Enter the pathname <volume>.TIPEN.TFINTLN1 or <volume>.TIPEN.TFINTLN2, depending on the language you want.
- 6. Proceed to Section 5 to complete the installation.

Section 5

Installing International TIPE

5.1 INTRODUCTION

Before installing the international version of TIPE, ensure that the United States version has been successfully installed.

NOTE

If you have already installed the United States and international versions and now wish to install a different international version, you must repeat the process; that is, install the United States version, then install the international version.

directories TFINTLN1 and TFINTLN2 contain the installation procedures for the following languages:

- * TFINTLN1 is the directory for:
 - German
 - Danish
 - Spanish
 - French
 - Italian
- * TFINTLN2 is the directory for:
 - Norwegian
 - Dutch
 - Swedish
 - Finnish

A special SCI command library is included in this package to aid you in the installation of an international version of the TIPE program. This special SCI command library is established as the secondary library. All system SCI commands are functional while the special SCI command library is active.

Use the following procedure to install International TIPE:

- 1. Activate the special SCI command entering the .USE command as follows:
 - a. If you are installing a language from the TFINTLN1 directory, enter the .USE command as follows:
 - [] .USE TFINTLN1.S\$CMDS,.S\$CMDS

While the special SCI command library is in effect, the following menu is displayed on your screen:

TIPE INTERNATIONAL

INSTALLATION

COMMANDS

<VERSION: 2.1.0 83342>

+----+ : Country : Language & State : Code : : INSTALL - Int'l installation : D : German (Germany) : procedure : DK : Danish (Denmark) : E : Spanish (Spain) : RTN - Return : F : French (France) : I : Italian (Italy) : +-----

> Make a note of your country code before executing INSTALL

- b. If you are installing a language from the TFINTLN2 directory, enter the .USE command as follows:
 - [] .USE TFINTLN2.S\$CMDS,.S\$CMDS

While the special SCI command library is in

effect, the following menu is displayed on your screen:

TIPE INTERNATIONAL

INSTALLATION

C O M M A N D S

<VERSION: 2.1.0 83342>

+----+ : Country : Language & State : : Code : +----+

> Make a note of your country code before executing INSTALL

5.2 INSTALL TIPE INTERNATIONAL

Install the TIPE program for the language you selected as follows:

- l. Enter INSTALL after the SCI prompt ([]):
 - [] INSTALL

2. Respond to the INSTALL prompts as follows:

Install International TIPE (Version 2.1.0 83342) COUNTRY CODE: <country code> INSTALLATION DISK: TFINTLNx SYSTEM DISK VOLUME: <volume> DESTINATION VOLUME: <volume> BATCH LISTING VOLUME: <volume>

- COUNTRY CODE: Enter the country code for the language you want. For example, enter D to install the German version of TIPE.
- INSTALLATION DISK: Enter the volume name TFINTLN1 or TFINTLN2 depending on the diskette inserted in the drive.
- SYSTEM DISK VOLUME: Enter the name of the system disk that will be installed when you use the TIPE program. The message file associated with the language you selected is copied to this disk.
- DESTINATION VOLUME: Enter the name of the volume where the TIPE software is already installed.
- BATCH LISTING VOLUME: Enter the name of the volume where the international batch installation directory will be created. During execution of the INSTALL command a directory called .LSTINTL is created on this volume. The following list shows how this directory is structured. This directory can be deleted when the first test is completed successfully. In this list (volume) is the volume name you entered in response to this prompt. If this directory has already been created. an error >0026 will be reported at the completion of the installation. This error can be ignored.
 - <volume>.LSTINTL.INSTALL is the name of the file containing the result of the INSTALL batch listing.
 - <volume>.LSTINTL.PATCHl is the name of the file containing the result of the PATCH1 batch listing.
 - <volume>.LSTINTL.PATCH2 is the name

of the file containing the result of the PATCH2 batch listing.

15 3. The installation takes about minutes complete. When the installation completes successfully the following messages are displayed:

TIPE editor installation completed with 0 errors

TIPE print installation completed with 0 errors

You can proceed to the next step. Ιf the installation is not successful the following errors are possible:

a. If an invalid country code is entered the following message is displayed:

An invalid country code was entered

country code and reenter the Check the INSTALL command.

b. If an error occurred during installation of the following messages is displayed:

TIPE editor installation completed with nn errors

TIPE print installation completed with nn errors

In these messages nn is the number of errors that occurred. You must return to step 1 of paragraph 3.1 and repeat the complete installation procedure.

- 4. After the INSTALL command executes you can print parameters of the language installed by executing the Print File (PF) command as follows:
 - [] PF

PF PRINT FILE

FILE PATHNAME(S): TFINTLNx. < country code > . APPENDIX

ANSI FORMAT?: YES LISTING DEVICE: LP01

DELETE AFTER PRINTING?: NO NUMBER OF LINES/PAGE: 62

FORM: STANDARD

NUMBER OF COPIES: 1

BANNER SHEET?: NO

Respond to the prompts as follows:

- * FILE PATHNAME(S): Enter the pathname of the file containing the appendix for the language installed. The volume name is the volume you entered in response to the INSTALLATION DISK prompt of the INSTALL command, either TFINTLN1 or TFINTLN2. <country code> is the country code you entered in response to the COUNTRY CODE prompt of the INSTALL command.
- * ANSI FORMAT?: Enter YES to specify ANSI format.
- * LISTING DEVICE or CLASS: The device name where the APPENDIX is printed. Be sure that the printer supports Upper/Lower characters. The default is LPO1.
- * DELETE AFTER PRINTING?: Enter NO for this prompt.
- NUMBER OF LINES/PAGE: Enter the number of lines to be printed on one page. The default is 62.
- FORM: Enter STANDARD for this prompt.
- * NUMBER OF COPIES: Enter the number of copies to be printed. The default is one.
- * BANNER SHEET?: Enter NO for this prompt.

5.3 UNLOAD TIPE INSTALLATION DISK

If you install TIPE from magnetic tape, simply unload the magnetic tape and refer to paragraph 5.4 to complete the installation. However, if you installed TIPE from a disk, you must unload the disk before using TIPE. You must also return to the system SCI command library. Proceed as follows:

1. To return to the system command library where will unload the disk, enter the special command RTN after the SCI prompt ([]):

[] RTN

2. To unload the disk, enter the SCI command Unload Volume (UV) after the SCI prompt ([]):

[] UV

3. Respond to the UV prompt as follows:

UNLOAD VOLUME VOLUME NAME: <volume>

* VOLUME NAME: Enter the volume name of the TIPE installation disk.

5.4 MODIFY COUNTRY CODE

CAUTION

| Incorrect use of the MCC command can cause key indexed files | (KIFs) to become nonusable. Before continuing with this | | section, refer to the MCC explanation in the DNOS Operations | | Guide, part number 2270502-9701, consult your system manager, | | and ensure that all users are logged off.

+-----

If TIPE is the first program installed on your system, or if you are reinstalling the object, you must modify the country code for your system.

To modify the country code for your system use the following steps:

1. Enter the SCI command Modify Country Code (MCC) as follows:

[]MCC

2. Respond to the prompts as follows:

MODIFY COUNTRY CODE COUNTRY NAME: <country code> OUTPUT ACCESS NAME:

- * COUNTRY NAME: Enter the country code for your system. You can specify any of the abbreviations or country names listed in Table 4-1. For example, you can enter either SWEDEN or only the letter S. Notice that in most cases the country codes for the MCC command differ from the country codes used with the TIPE INSTALL command.
- * OUTPUT ACCESS NAME: Accept the default for this prompt, which is your terminal.

Table 4-1 Country Codes for the MCC Command

| Abbreviation | Country |
|--------------|-------------------------------|
| DE | Denmark |
| FI | Finland |
| FWP | France Word Processing |
| GE | Germany |
| NOR | Norway |
| SW | Sweden |
| SP | Spain |
| US | United States, Holland, Italy |

5.5 TIPE INTERNATIONAL VERIFICATION

This completes the installation of the international version of the TIPE program. Verify the installation by entering the TIPE command in response to the SCI command prompt ([]). When the TIPE main menu is displayed on your screen in the language specified by the country code, the software has been successfully installed on your system. The directory <volume>.LSTINTL can be deleted from the disk. Enter the Delete Directory (DD) command and respond to the prompts as follows:

[]DD

DELETE DIRECTORY

PATHNAME: <volume>.LSTINTL

LISTING ACCESS NAME: ARE YOU SURE?: YES

In this command <volume > is the volume name you entered in response to the BATCH LISTING VOLUME prompt in paragraph 5.2.